NAG Library Function Document

nag sparse herm basic diagnostic (f11gtc)

1 Purpose

nag_sparse_herm_basic_diagnostic (f11gtc) is the third in a suite of three functions for the iterative solution of a complex Hermitian system of simultaneous linear equations (see Golub and Van Loan (1996)). nag_sparse_herm_basic_diagnostic (f11gtc) returns information about the computations during an iteration and/or after this has been completed. The first function of the suite, nag_sparse_herm_basic_setup (f11grc), is a setup function, the second function, nag_sparse_herm_basic_solver (f11gsc) is the proper iterative solver.

These three functions are suitable for the solution of large sparse complex Hermitian systems of equations.

2 Specification

3 Description

nag_sparse_herm_basic_diagnostic (f11gtc) returns information about the solution process. It can be called both during a monitoring step of the solver nag_sparse_herm_basic_solver (f11gsc) or after this solver has completed its tasks. Calling nag_sparse_herm_basic_diagnostic (f11gtc) at any other time will result in an error condition being raised.

For further information you should read the documentation for nag_sparse_herm_basic_setup (fl1grc) and nag sparse herm basic solver (fl1gsc).

4 References

Golub G H and Van Loan C F (1996) *Matrix Computations* (3rd Edition) Johns Hopkins University Press, Baltimore

5 Arguments

1: itn – Integer *

On exit: the number of iterations carried out by nag sparse herm basic solver (fl1gsc).

2: **stplhs** – double * Output

On exit: the current value of the left-hand side of the termination criterion used by nag sparse herm basic solver (fl1gsc).

3: **stprhs** – double * Output

On exit: the current value of the right-hand side of the termination criterion used by nag_sparse_herm_basic_solver (fl1gsc).

Mark 25 f11gtc.1

fl1gtc NAG Library Manual

4: **anorm** – double * Output

On exit: the norm $\|A\|_1 = \|A\|_{\infty}$ when either it has been supplied to nag_sparse_herm_basic_setup (fllgrc) or it has been estimated by nag_sparse_herm_basic_solver (fllgsc) (see also Sections 3 and 5 in nag_sparse_herm_basic_setup (fllgrc)).

Otherwise, $\mathbf{anorm} = 0.0$ is returned.

5: sigmax – double * Output

On exit: the current estimate of the largest singular value $\sigma_1(\bar{A})$ of the preconditioned iteration matrix $\bar{A} = E^{-1}AE^{-H}$, when either it has been supplied to nag_sparse_herm_basic_setup (f11grc) or it has been estimated by nag_sparse_herm_basic_solver (f11gsc) (see also Sections 3 and 5 in nag_sparse_herm_basic_setup (f11grc)). Note that if **its** < **itn** then **sigmax** contains the final estimate. If, on final exit from nag_sparse_herm_basic_solver (f11gsc), **its** = **itn**, then the estimation of $\sigma_1(\bar{A})$ may have not converged: in this case you should look at the value returned in **sigerr**. Otherwise, **sigmax** = 0.0 is returned.

6: its - Integer * Output

On exit: the number of iterations employed so far in the computation of the estimate of $\sigma_1(\bar{A})$, the largest singular value of the preconditioned matrix $\bar{A} = E^{-1}AE^{-H}$, when $\sigma_1(\bar{A})$ has been estimated by nag_sparse_herm_basic_solver (f11gsc) using the bisection method (see also Sections 3, 5 and 9 in nag_sparse_herm_basic_setup (f11grc)). Otherwise, its = 0 is returned.

7: sigerr – double * Output

On exit: if $\sigma_1(\bar{A})$ has been estimated by nag_sparse_herm_basic_solver (fl1gsc) using bisection,

$$\mathbf{sigerr} = \max\left(\frac{\left|\sigma_1^{(k)} - \sigma_1^{(k-1)}\right|}{\sigma_1^{(k)}}, \frac{\left|\sigma_1^{(k)} - \sigma_1^{(k-2)}\right|}{\sigma_1^{(k)}}\right),$$

where k = its denotes the iteration number. The estimation has converged if $sigerr \le sigtol$ where sigtol is an input argument to nag_sparse_herm_basic_setup (fl1grc). Otherwise, sigerr = 0.0 is returned.

8: work[lwork] – const Complex

Communication Array

On entry: the array work as returned by nag_sparse_herm_basic_solver (f11gsc) (see also Section 3 in nag sparse herm basic solver (f11gsc)).

9: **lwork** – Integer *Input*

On entry: the dimension of the array work (see also Section 5 in nag_sparse_herm_basic_setup (f11grc)).

Constraint: **lwork** \geq 120.

Note: although the minimum value of **lwork** ensures the correct functioning of nag_sparse_herm_basic_diagnostic (fl1gtc), a larger value is required by the iterative solver nag_sparse_herm_basic_solver (fl1gsc) (see also Section 5 in nag_sparse_herm_basic_setup (fl1grc)).

10: fail – NagError * Input/Output

The NAG error argument (see Section 3.6 in the Essential Introduction).

f11gtc.2 Mark 25

6 Error Indicators and Warnings

NE_ALLOC_FAIL

Dynamic memory allocation failed.

See Section 3.2.1.2 in the Essential Introduction for further information.

NE BAD PARAM

On entry, argument \(\value \rangle \) had an illegal value.

NE_INT

```
On entry, lwork = \langle value \rangle. Constraint: lwork > 120.
```

NE_INTERNAL_ERROR

An internal error has occurred in this function. Check the function call and any array sizes. If the call is correct then please contact NAG for assistance.

An unexpected error has been triggered by this function. Please contact NAG. See Section 3.6.6 in the Essential Introduction for further information.

NE NO LICENCE

Your licence key may have expired or may not have been installed correctly. See Section 3.6.5 in the Essential Introduction for further information.

NE OUT OF SEQUENCE

nag sparse herm basic diagnostic (fl1gtc) has been called out of sequence.

7 Accuracy

Not applicable.

8 Parallelism and Performance

Not applicable.

9 Further Comments

None.

10 Example

See Section 10 in nag sparse herm basic setup (fl1grc).

Mark 25 f11gtc.3 (last)